

IPv6 Security Lab - Netflow

Exploring Netflow

Netflow identifies anomalous and security-related network activity by tracking network flows. NetFlow data can be viewed and analysed via the command line interface (CLI), or the data can be exported to a commercial or freeware NetFlow collector for aggregation and analysis. NetFlow collectors, through long-term trending, can provide network behaviour and usage analysis. NetFlow functions by performing analysis on specific attributes within IP packets and creating flows. Version 5 is the most commonly used version of NetFlow, however, version 9 is more extensible and is required to support IPv6. NetFlow flows can be created using sampled traffic data in high-volume environments. Cisco Express Forwarding (CEF) is a prerequisite to enabling NetFlow.

NetFlow can be configured on routers and switches. In older releases of Cisco IOS software, the command to enable NetFlow on an interface was:

```
ip route-cache flow
```

In newer releases of Cisco IOS (12.4 onwards), the command has been replaced by:

```
ip flow {ingress | egress}
```

The following configuration illustrates the basic configuration of this feature.

```
ip flow-export destination <ip-address> <udp-port>
ip flow-export version <version>
!
interface fastethernet 0/0
  ip flow ingress
  ip flow egress
!
```

The following is an example of NetFlow output from the router command line interface. The SrcIf attribute can aid in traceback.

```
router#show ip cache flow
IP packet size distribution (26662860 total packets):
  1-32   64   96   128   160   192   224   256   288   320   352   384   416   448
480
  .741 .124 .047 .006 .005 .005 .002 .008 .000 .000 .003 .000 .001 .000
.000

  512   544   576   1024  1536  2048  2560  3072  3584  4096  4608
  .000 .000 .001 .007   .039   .000   .000   .000   .000   .000   .000

IP Flow Switching Cache, 4456704 bytes
```

55 active, 65481 inactive, 1014683 added 41000680 afer polls, 0 flow alloc failures Active flows

timeout in 2 minutes Inactive flows timeout in 60 seconds

IP Sub Flow Cache, 336520 bytes
 110 active, 16274 inactive, 2029366 added, 1014683 added to flow
 0 alloc failures, 0 force free
 1 chunk, 15 chunks added
 last clearing of statistics never

Protocol	Total Flows	Flows /Sec	Flows /Sec	Packets /Flow	Bytes /Pkt	Packets /Sec	Active(Sec) /Flow	Idle(Sec) /Flow
TCP-Telnet	11512	0.0	0.0	15	42	0.2	33.8	44.8
TCP-FTP	5606	0.0	0.0	3	45	0.0	59.5	47.1
TCP-FTPD	1075	0.0	0.0	13	52	0.0	1.2	61.1
TCP-WWW	77155	0.0	0.0	11	530	1.0	13.9	31.5
TCP-SMTP	8913	0.0	0.0	2	43	0.0	74.2	44.4
TCP-X	351	0.0	0.0	2	40	0.0	0.0	60.8
TCP-BGP	114	0.0	0.0	1	40	0.0	0.0	62.4
TCP-NNTP	120	0.0	0.0	1	42	0.0	0.7	61.4
TCP-other	556070	0.6	0.6	8	318	6.0	8.2	38.3
UDP-DNS	130909	0.1	0.1	2	55	0.3	24.0	53.1
UDP-NTP	116213	0.1	0.1	1	75	0.1	5.0	58.6
UDP-TFTP	169	0.0	0.0	3	51	0.0	15.3	64.2
UDP-Frag	1	0.0	0.0	1	1405	0.0	0.0	86.8
UDP-other	86247	0.1	0.1	226	29	24.0	31.4	54.3
ICMP	19989	0.0	0.0	37	33	0.9	26.0	53.9
IP-other	193	0.0	0.0	1	22	0.0	3.0	78.2
Total:	1014637	1.2	1.2	26	99	32.8	13.8	43.9

SrcIf Pkts	SrcIPaddress	DstIf	DstIPaddress	Pr	SrcP	DstP
Gi0/1 07A	192.168.128.21 3	Local	192.168.128.20	11	CB2B	
Gi0/1 55	192.168.150.60	Gi0/0	10.89.17.146	06	0016	101F
Gi0/0 0016	10.89.17.146 9	Gi0/1	192.168.150.60	06	101F	
Gi0/1 11	192.168.150.60	Local	192.168.206.20	01	0000	0303
Gi0/0 0016	10.89.17.146 1	Gi0/1	192.168.150.60	06	07F1	

Netflow for IPv4

To get some practice, we will first turn on Netflow for IPv4. The IPv4 command set uses Cisco's original Netflow configuration. For IPv6 flow information, we can only use Flexible Netflow, and we will try that out in the next section.

Activating Netflow for IPv4

Each Group should turn on Netflow on the border router of their AS. To do this, simply go to the border interface and do something similar to this:

```
interface fastethernet 0/0
  ip flow ingress
  ip flow egress
!
```

Once this has been running for a few minutes, commands like “show ip cache flow” will display output similar to that from the introduction above. To create traffic for Netflow to see, try some ICMPs, traceroutes, and even telnet or ssh to other routers in the lab. This will generate traffic, and the info will persist in Netflow’s cache for a few minutes.

Top talkers in Netflow

Each team should also configure a set of top-talkers, to see what the busiest source and destinations are. Try this configuration:

```
ip flow-top-talkers
  top 20
  sort-by bytes
```

This displays the top 20 talkers, sorting them in descending order of bytes transferred.

Try some of the other CLI options available under the ip flow-top-talkers configurations. There are many match options:

```
gw(config-flow-top-talkers)# match ?
  byte-range      Match a range of bytes
  class-map       Match a class
  destination     Match destination criteria
  direction       Match direction
  flow-sampler    Match a flow sampler
  input-interface  Match input interface
  nexthop-address Match next hop
  output-interface Match output interface
  packet-range    Match a range of packets
  protocol        Match protocol
  source          Match source criteria
  tos             Match TOS
```

Try some of these and see what happens to the output.

Netflow for IPv6

Cisco IOS used to support IPv6 with standard Netflow. But this was only briefly the case in IOS 12.3 and 12.4. From 12.4T onwards, IPv6 support in Netflow was replaced by Flexible Netflow for IPv6 (it is also available for IPv4).

Activating Netflow for IPv6

The configuration syntax for Flexible Netflow is somewhat different and a lot more sophisticated. First off we need to create Flow Monitors for our incoming and outgoing Netflow captures. Here is an example

```
flow monitor FLOW-MONITOR-V6-IN
  cache timeout active 300
  record netflow ipv6 original-input
!
flow monitor FLOW-MONITOR-V6-OUT
  cache timeout active 300
  record netflow ipv6 original-output
!
```

And then we apply these flow monitors to the interface we want to monitor:

```
interface FastEthernet0/0
  ipv6 flow monitor FLOW-MONITOR-V6-IN input
  ipv6 flow monitor FLOW-MONITOR-V6-OUT output
!
```

Top talkers in Flexible Netflow

The top talkers in the Flexible Netflow configuration is somewhat different – there is no need to create a specific stanza to set up the top talkers as the router can simply display the top talkers from the command line. Here is an example

```
show flow monitor FLOW-MONITOR-V6-OUT cache aggregate \
  ipv6 source address ipv6 destination address sort counter \
  bytes top 20
```

This is all one command line and displays the top 20 talkers for outbound traffic, sorting them in descending order of bytes transferred. The command above can be modified to look at the inbound traffic also, by using the inbound flow monitor.


Summary

While this exercise has shown how to set up Netflow for both IPv4 and IPv6, it has a more serious aspect. It is possible for a network operator to very simply see what traffic is traversing their network. It is very easy to spot malicious activity, scanning, etc, simply by looking at the flow data and searching for particular signatures (tcp or udp ports, addresses, etc). This makes Netflow a valuable security tool for all network operators, whether they are running an IPv4-only network, or are dual stack IPv4 and IPv6.

Try some of the other CLI options available under the `show flow monitor` command.

From:

<https://www.bgp4all.com/pfs/> - Philip Smith's Internet Development Site



Permanent link:

<https://www.bgp4all.com/pfs/training/itu-ipv6-2018/7-netflow?rev=1523169983>

Last update: **2018/04/08 06:46**